Barista Control Numbering

The following barista.cfg entries specify the control numbering used by Barista. Bolded entries specify starting numbers for ranges. All others are specific numbers for one control per form.

```
+TEXT CTL=2000
+ENTRY_CTL=3000
+DISPLAY_CTL=4000
+IMAGE_CTL=6000
+STATUS CTL=10000
+PROGRESS CTL=10010
+WINDOW RES=1000
+TAB CTL=1050
+BLOCK_CTL=19000
+BLOCK_TEXT_CTL=19500
+CHILD WIN=1100
+GRID CTL=5000
+GRID LIST CTL=7000
+BUTTON CTL=20000
+BACKGROUND CTL=19990
+CUSTOM_CTL=25000
+NAVBAR CTL=1500
+DETAIL GRID WIN=1109
```

Barista toolbar and menubar functions use the 31000 range. The actual control IDs for these functions can be found in the barista.ini file.

Text, entry, display and button control numbers correspond to the entry order sequence of the column, and the window (or child window) on which it's located. The ranges can be explained by using the following format, where "w" equals the window ID and "nn" equals the entry sequence number:

```
+CHILD_WIN=110w

+TEXT_CTL=2wnn

+ENTRY_CTL=3wnn

+DISPLAY_CTL=4wnn

+IMAGE_CTL=6wnn

+BUTTON_CTL=20wnn

Find = 20wnn

Calendar = 21wnn

Drilldown = 22wnn

Link = 23wnn

Multi-Language = 24wnn
```

For example, if the first column on a non-tabbed form had a static text label, entry control, validation display and and an inquiry button, the following controls would be used for that column:

Static text: 2001 Entry control: 3001 Display control: 4001 Inquiry "Find" button: 20001

The second column on the form would use:If

Static text: 2002 Entry control: 3002 Display control: 4002

Inquiry "Find" button: 20002

If the third column were on the first tab (child window), the following numbers would be used:

Child window: 1101 Static text: 2101 Entry control: 3101
Display control: 4101
Inquiry "Find" button: 20101